

INSTRUCTIONS FOR LOADING THE PRODUCT TABLE

Inoxpa Pump Selector only has 'water' as the liquid available in the table that the programme installs by default.

Step 1 of 5 - Fluid Properties

Fluid

Select a fluid from the list of tables, or enter the name of a fluid.

Installed fluid tables:

Water

Custom fluid:

Properties

Enter the fluid temperature. Fluid tables automatically generate properties, for custom fluids you can enter properties.

Temperature: °C

Density: kg/m³

Viscosity: cP


Vapor pressure: kPa a

< Atrás Siguiete > Cancelar Ayuda


A personalised product table has been created for greater programme versatility. It is the 'Tabla de productos' folder, and it is very easy to install.

To install it correctly, follow the steps below:

- Copy the folder to C:\Users\user name\Documents\My Engineering Files\Tables



- Start up the programme. In the 'tools' menu in the menu bar, select 'Preferences'. In the 'Tables' entry, select 'Tabla de productos' and clic on 'aceptar' or 'OK' until all the windows are closed.



- Finally, restart the programme, and you will then have a table with all the products.

